

# Glacier Sim

version 2

Wendy Adams, Bob Anderson, Andrea Bair,  
Chris Malley, Archie Paulson, Kathy Perkins

Oct 30, 2007

<http://www.colorado.edu/physics/EducationIssues/archie/GlacierSim/>

# Changes in Version 2

Changes in approximate order of importance:

- 3-panel zoom interface
  - three panels 'map view' on top, 'main view' in the middle, and control panel at the bottom
  - main view changes when the little box in map view is dragged
- climate controls now have options for setting rates of climate change
- tools are now in a toolbox, whence they may be dragged out and placed on the glacier or valley floor.
- new tools:
  - flag control (click on flag for info); only red flags; flags stick into ice a little bit; marker flags say 'right click for info!' when they're planted
  - ice thickness measure (calipers-like)
  - trash can (to remove tools)
- crystals in ice and texture on the snow (will move with the ice velocity)
- mass balance function appears on-screen (no popup)
- top of glacier looks like ice below ELA and white snow above

# Changes in Version 2

## continued...

- no longer any option to change valley floor
- elevation line altitude (red dotted line) shown horizontally through the ice, along the top of the glacier, and on the map view
- changed climate controls to standard radio buttons
- aspect ratio is 1024x768
- no more option to change shape of valley floor
- perspective change (no longer coming out of the plane of the sim)
- new view checkbox "view follows terminus" (will be on by default)
- 'Set Glacier to Equilibrium' button now on the bottom
- time controls now standard (as in quantum bound states)
- reset -> restart
- new 'reset all' button
- show -> view


# Basic Model

(these will be provided in greater detail soon)

- The glacier's thickness versus position and time depend on
  - shape/slope of valley floor
  - temperature (a linear function of elevation)
  - precipitation rate (also a linear function of elevation)
- Temperature and precipitation can be combined to form a function called the mass balance, which equals growth (due to precip.) minus ablation (melt and sublimation). The mass balance gives the rate of change of glacier height per unit time as a function of elevation.
- A mass balance which is constant in time results (eventually) in a steady-state glacier. In steady state, the glacier is flowing downhill as it gains ice over its upper half (positive mass balance) and loses ice over its lower half (negative mass balance). The line that divides these two regions is called the “equilibrium line”.

The velocity of the ice is nonzero at the bottom of the glacier (due to sliding), and increases with vertical height, as shown in the figure at the right. A simple model can be seen at the following website:


[http://www2.wvnorton.com/college/geo/egeo/flash/18\\_1.swf](http://www2.wvnorton.com/college/geo/egeo/flash/18_1.swf)



# Glaciers

Java Application Window

File Help



### Toolbox

thermometer   snowfall gauge   marker flags   ice thickness measuring tool   trash

### View:

<input type="checkbox"/> equilibrium line	<input type="checkbox"/> view follows terminus
<input type="checkbox"/> ice velocities	<input type="checkbox"/> mass balance
<input type="checkbox"/> debris	<input type="checkbox"/> terminus tracker
<input type="checkbox"/> snowfall	<input type="checkbox"/> ruler
<input type="checkbox"/> coordinates	<input type="checkbox"/> borehole drill

### Climate Controls:


<input checked="" type="radio"/> Snowfall & Temperature	<b>Present Day:</b> Equilibrium Line Altitude <input type="text" value="3000"/> m	<b>Change To:</b> Equilibrium Line Altitude <input type="text" value="3000"/> m
<input type="radio"/> Climate Presets	Mass Balance Slope <input type="text" value="10"/> m/yr/km	in
<input type="radio"/> Mass Balance	Maximum Mass Balance <input type="text" value="2.0"/> m/yr	<input type="text" value="10,000"/> years

123.57 years  slow fast   **Restart**   **Reset All**   **Pause**   **Set Glacier to Equilibrium**   **Help!**

# Glaciers

Java Application Window


File Help



little box shows which section of the valley is shown in the middle panel

top panel shows map view of entire glacier valley

middle panel shows glacier cross section



texture shown in and on glacier – moves with ice velocity

glacier color changes slightly at the equilibrium line

toolbox in play area

## Toolbox



thermometer

snowfall gauge

marker flags

ice thickness measuring tool

trash

bottom panel is the control panel



## Climate Controls:

- Snowfall & Temperature
- Climate Presets
- Mass Balance

### Present Day:

Equilibrium Line Altitude  m  
Mass Balance Slope  m/yr/km  
Maximum Mass Balance  m/yr

### Change To:

Equilibrium Line Altitude  m  
in  
 years

123.57 years  slow fast

**Restart**

**Reset All**

**Pause**

**Set Glacier to Equilibrium**

**Help!**

# Glaciers

Java Application Window

File Help

After glacier retreat

These little snow patches are just part of the background

Moraine (rock) wall left behind

## Toolbox



thermometer



snowfall gauge



marker flags



ice thickness measuring tool



trash

## View:

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates
- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

## Climate Controls:

- Snowfall & Temperature
- Climate Presets
- Mass Balance

### Present Day:

Equilibrium Line Altitude  m  
Mass Balance Slope  m/yr/km  
Maximum Mass Balance  m/yr

### Change To:

Equilibrium Line Altitude  m  
in  
 years



123.57 years



slow

fast

Restart

Reset All

Pause

Set Glacier to Equilibrium

Help!


# Glaciers

Java Application Window

File Help



After the glacier has grown.



## Toolbox

thermometer	snowfall gauge	marker flags	ice thickness measuring tool	trash

## View:

- |   |   |
|---|---|
| <input type="checkbox"/> equilibrium line | <input checked="" type="checkbox"/> view follows terminus |
| <input type="checkbox"/> ice velocities   | <input type="checkbox"/> mass balance                     |
| <input type="checkbox"/> debris           | <input type="checkbox"/> terminus tracker                 |
| <input type="checkbox"/> snowfall         | <input type="checkbox"/> ruler                            |
| <input type="checkbox"/> coordinates      | <input type="checkbox"/> borehole drill                   |

## Climate Controls:

- Snowfall & Temperature
- Climate Presets
- Mass Balance

### Present Day:

Equilibrium Line Altitude	<input type="text" value="3000"/>	m
Mass Balance Slope	<input type="text" value="10"/>	m/yr/km
Maximum Mass Balance	<input type="text" value="2.0"/>	m/yr

### Change To:

Equilibrium Line Altitude	<input type="text" value="3000"/>	m
	<input type="text" value="in"/>	
	<input type="text" value="10,000"/>	years



123.57 years



Restart

Reset All

Pause

Set Glacier to Equilibrium

Help!

# Glaciers

Java Application Window


File Help



If the glacier has grown this box can be dragged to see the terminus (lower end) of the glacier. The box can also be dragged to any point in the valley.

This checkbox (checked by default) makes the middle panel follow the glacier terminus, otherwise the view stays at the same place in the valley.

The blue line shows the glacier's length.



## Toolbox



thermometer



snowfall gauge



mass balance



ice thickness measuring tool



trash

## View:

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates
- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

## Climate Controls:

- Snowfall & Temperature
- Climate Presets
- Mass Balance

### Present Day:

Equilibrium Line Altitude  m  
Mass Balance Slope  m/yr/km  
Maximum Mass Balance  m/yr

### Change To:

Equilibrium Line Altitude  m  
  
 years



123.57 years



Restart

Reset All

Pause

Set Glacier to Equilibrium

Help!

# Climate Controls

- The control panel on the right panel controls climate by one of three methods (selected by radio buttons)
  - snowfall and temperature controlled independently (previous slides)
  - climate presets (in drop-down boxes) are selectors for certain values of snowfall & temperature (next slide):
    - “Epoch” can be “modern day” or “last glacial maximum”
    - “latitude” can be “equitorial” or “temperate” or “polar”
    - “altitude” can be “sea level” or “alpine”
  - edit mass balance by entering the three numeric values that are used to describe the function (after next slide):
    - altitude of the equilibrium line
    - slope of the linear mass balance function
    - maximum value of the mass balance
- Each climate control has an additional setting for controlling the rate of change of parameters
- Once a climate control is changed, the glacier can be set to be at the steady-state shape for the current climate by pressing the button next to “Set glacier to equilibrium state.” Otherwise, the glacier will evolve in time until the steady-state is eventually achieved.

# Glaciers

Java Application Window

File Help



Snowfall & Temperature controlled independently

Can also set their rates of change here

## Toolbox



thermometer



snowfall gauge



marker flags



ice thickness measuring tool



trash

## View:

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates
- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

## Climate Controls:

- Snowfall & Temperature
- Climate Presets
- Mass Balance

### Present Day:

Snowfall  
none  lots

Temperature  
cold  hot

### Rate of Change:

Snowfall Change  m/yr

Temperature Change  °C/yr



123.57 years

slow  fast

Restart

Reset All

Pause


Set Glacier to Equilibrium

Help!

# Glaciers

Java Application Window

File Help



Climate presets set the snowfall & temp. according to some time and place

Change control is slightly different

### Toolbox

thermometer   snowfall gauge   marker flags   ice thickness measuring tool   trash

### View:

<input type="checkbox"/> equilibrium line	<input checked="" type="checkbox"/> view follows terminus
<input type="checkbox"/> ice velocities	<input type="checkbox"/> mass balance
<input type="checkbox"/> debris	<input type="checkbox"/> terminus tracker
<input type="checkbox"/> snowfall	<input type="checkbox"/> ruler
<input type="checkbox"/> coordinates	<input type="checkbox"/> borehole drill

### Climate Controls:


<input type="radio"/> Snowfall & Temperature	Present Day: Epoch <input type="text" value="modern day"/>	Change To: Epoch <input type="text" value="modern day"/>
<input type="radio"/> Climate Presets	Latitude <input type="text" value="polar"/>	
<input type="radio"/> Mass Balance	Altitude <input type="text" value="alpine"/>	in <input type="text" value="10,000"/> years

🕒 123.57 years   slow ————— fast   **Restart**   **Reset All**   **Pause**   **Set Glacier to Equilibrium**   **Help!**

# Glaciers

Java Application Window

File Help



Directly edit the mass balance function

The ELA can change in time

## Toolbox

thermometer snowfall gauge marker flags ice thickness measuring tool trash

## View:

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates
- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

## Climate Controls:

- Snowfall & Temperature
- Climate Presets
- Mass Balance

### Present Day:

Equilibrium Line Altitude  m  
Mass Balance Slope  m/yr/km  
Maximum Mass Balance  m/yr

### Change To:

Equilibrium Line Altitude  m  
in  
 years

 123.57 years  slow fast

 Restart

 Reset All

 Pause

 Set Glacier to Equilibrium

 Help!

# “View” Options


In the “View” panel, the user can click one or more of the boxes. Results shown in the following slides.

- “equilibrium line” shows the altitude of zero mass balance.
- “ice velocities” shows a vector field of current ice velocity at all positions within the ice.
- “debris” shows rocks which will flow along with the ice velocity and be deposited at the terminus.
- “snowfall” will show the animated falling snow above the equilibrium line altitude (ELA).
- “coordinates” will show elevation on the vertical axis and distance on the horizontal axis.
- “mass balance” will pop up a window that shows the mass balance function.
- “terminus tracker” will show an arrow with the current horizontal position and velocity of the glacier terminus.
- “ruler” can be used to measure down-slope distance
- “borehole drill” is a tool to drill vertical boreholes in the ice. It will start out as a vertical column and then deform, showing the differential velocities of the ice flow (shown in figure).

# Glaciers

Java Application Window

File Help



ELA should also be shown on map view

Equilibrium line and velocities checked on

Ice velocity vectors

Equilibrium Line Altitude (ELA)

**Toolbox**

- thermometer
- snowfall gauge
- marker flags
- ice thickness measuring tool
- trash

**View:**

<input checked="" type="checkbox"/> equilibrium line	<input checked="" type="checkbox"/> view follows terminus
<input checked="" type="checkbox"/> ice velocities	<input type="checkbox"/> mass balance
<input type="checkbox"/> debris	<input type="checkbox"/> terminus tracker
<input type="checkbox"/> snowfall	<input type="checkbox"/> ruler
<input type="checkbox"/> coordinates	<input type="checkbox"/> borehole drill

**Climate Controls:**


• Snowfall & Temperature	<b>Present Day:</b>	<b>Change To:</b>
	Equilibrium Line Altitude <input type="text" value="3000"/> m	Equilibrium Line Altitude <input type="text" value="3000"/> m
	Mass Balance Slope <input type="text" value="10"/> m/yr/km	in
• Climate Presets	Maximum Mass Balance <input type="text" value="2.0"/> m/yr	<input type="text" value="10,000"/> years
• Mass Balance		

123.57 years  slow fast

# Glaciers

Java Application Window

File Help



View snowfall checked on

Snowfall density will depend on altitude. Would nice if it were animated.

Tool

- thermometer
- snowfall gauge
- marker flags
- ice thickness measuring tool
- trash

View

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates
- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

Climate Controls:

- Snowfall & Temperature
- Climate Presets
- Mass Balance

	Present Day:	Change To:
Equilibrium Line Altitude	<input type="text" value="3000"/> m	<input type="text" value="3000"/> m
Mass Balance Slope	<input type="text" value="10"/> m/yr/km	in
Maximum Mass Balance	<input type="text" value="2.0"/> m/yr	<input type="text" value="10,000"/> years

123.57 years   slow fast

**Restart**

**Reset All**

**Pause**


**Set Glacier to Equilibrium**

**Help!**

# Glaciers

Java Application Window

File Help



Coordinates shown (down-valley distance and elevation)

Rocks entrained in ice and riding along on top. The debris moves at the speed of the ice flow.

View debris and coordinates checked on

Debris deposited at terminus

Toolbox



thermometer



ice thickness measuring tool



trash

View:

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates
- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

Climate

- Snowfall & Temperature
- Climate Presets
- Mass Balance

Present Day:

Equilibrium Line Altitude  m

Mass Balance Slope  m/yr/km

Maximum Mass Balance  m/yr

Change To:

Equilibrium Line Altitude  m

in

years



123.57 years



slow

fast

Restart

Reset All

Pause

Set Glacier to Equilibrium

Help!

# Glaciers

Java Application Window

File Help

Borehole drill.  
Drills boreholes!



Older boreholes  
deform  
according to the  
local ice  
velocity

Ruler measures  
distance down-  
slope

View terminus  
tracker and  
borehole drill  
checked on

x=12.1 km  
advancing  
at 2.0 m/yr

“Terminus tracker” is an  
indicator that follows the  
terminus and reads out its  
length and rate of  
change of length




File Help

Mass balance appears with the same vertical coordinates as the display (mass balance equals zero at the ELA)

View mass balance and ruler checked on

Ruler measures distance down-slope



thermometer   snow gauge   marker flags   ice thickness measuring tool   trash

**View:**

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates
- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

**Present Day:**

- Equilibrium Altitude:  m
- Balance Slope:  m/yr/km
- Maximum Mass Balance:  m/yr

**Change To:**

- Equilibrium Line Altitude:  m
- in*
- years

🕒 123.57 years   slow   fast   ⏪ Restart   Reset All   ⏸ Pause   Set Glacier to Equilibrium   Help!

# Toolbox

In the “Toolbox” the user sees various tools that can be dragged onto the glacier. There can be multiple instances of any tool on the glacier. They are removed by dragging to the trash.

- “marker flag” allows the user to plant flags. On ice the flag will move with the ice flow. A flag can also be planted on the ground (to mark the terminus at some time, for example) – this flag can be covered and uncovered by the glacier. A right-click on any flag can give it's time of placement. It would be nice if there was a popup message appeared when dragging a flag out of the box to indicate that it has this right-click feature.
- “thermometer” gives a temperature-measuring tool. It reports the atmospheric temperature. It should be excluded from the cross-section region since we don't keep track of ice temperatures.
- “snow gauge” looks like a bucket. It can be dragged around and reports the local net snow accumulation.
- “ice thickness measuring tool” can be placed on the glacier to read out its thickness at some point

# Glaciers

Java Application Window

File Help

Flags stick into the glacier cross-section and move with the ice velocity.

Flags can be dragged out onto glacier

## Toolbox



thermometer



snowfall gauge



marker flags



ice thickness measuring tool



trash

## View:

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates

- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

## Climate Control

- Snowfall & Temperature
- Climate Present
- Mass Balance

## Present Day:

## Change To:

Equilibrium Line Altitude  
 m  
in  
 years

Flags (and all other tools from the toolbox) can be removed by dragging them to the trash



123.57 years

slow fast

Restart

Reset A

Set Glacier to Equilibrium

Help!

Snow gauges show rate of snow/ice accumulation.

Thermometers show local (adiabatic) temperature.

Any tool from the toolbox can have multiple instances



#### Toolbox



#### View:

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates
- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

#### Climate Controls:

- Snowfall & Temperature
- Climate Presets
- Mass Balance

#### Present Day:

Equilibrium Line Altitude  m  
Mass Balance Slope  m/yr/km  
Maximum Mass Balance  m/yr

#### Change To:

Equilibrium Line Altitude  m  
*in*  
 years



123.57 years




# Glaciers

Java Application Window

File Help

"Ice thickness measuring tool" snaps to glacier thickness



### Toolbox

thermometer   snowfall gauge   marker flags   ice thickness measuring tool   trash

### View:

- equilibrium line
- ice velocities
- debris
- snowfall
- coordinates
- view follows terminus
- mass balance
- terminus tracker
- ruler
- borehole drill

### Climate Controls:

	Present Day:	Change To:
• Snowfall & Temperature	Equilibrium Line Altitude <input type="text" value="3000"/> m	Equilibrium Line Altitude <input type="text" value="3000"/> m
• Climate Presets	Mass Balance Slope <input type="text" value="10"/> m/yr/km	<input type="text" value=""/> in
• Mass Balance	Maximum Mass Balance <input type="text" value="2.0"/> m/yr	<input type="text" value="10,000"/> years

123.57 years  slow fast

Restart

Reset All

Pause

Set Glacier to Equilibrium

Help!

## Other Options (which would be nice)

- show age of ice with contour lines (or colors?)
- velocity vectors could also appear on glacier surface to show lateral variation in flow
- option to change the slope or shape of the valley floor

# The End

That concludes the sim specification (as it exists so far). The remaining slides include motivations for this sim, including student difficulties, learning goals, and animations that exist on the web.

# Student learning difficulties/misconceptions

- Glaciers form only where it is very cold, and disappear with warming (not related to amount of snowfall)
- Glaciers only form at high elevations or latitudes (T control); cannot form near sea level or at low latitudes (perhaps more a problem in Colorado, where most instructor examples are of alpine glaciers).
- A glacier is a pile of ice that sits there once it forms; dynamics of ice movement in a “steady-state” glacier not known.
- Glacial retreat means that ice is not moving but just melting back, or that the ice is literally moving uphill.
- No sense of how long it takes glaciers to form, or change.
- More melting (more water) makes a glacier flow faster; thus, increased temperature can make the whole thing slide downhill.

# Learning Goals and objectives

- Describe how glaciers form, grow, and shrink – specify what environmental conditions lead to each.
  - Identify where net ablation ( $\sim$ melting $>$ snowfall) and accumulation ( $\sim$ melting $<$ snowfall) occur in relation to the Equilibrium Line Altitude (ELA).
  - Explain or illustrate how glaciers form.
  - Describe the most important controls on mass balance in a glacier.
  - Analyze the relationship between temperature and the likelihood of snow vs. rain at given parts of a glacier.
- Explain how ice moves within a glacier (describe and illustrate the mass balance of a glacier).
  - Describe and illustrate how glacial ice moves.
  - Qualitatively describe the relationship between the speed of ice flow and with ice thickness, and predict where ice is oldest.
- Describe why and how valley glaciers “advance” or “retreat”. When the glacier retreats, does ice move up the glacial valley?
  - Compare and contrast motion of ice when a glacier is (1) at equilibrium, (2) advancing, and (3) retreating.
  - Compare and contrast climatic conditions leading to glacial (1) equilibrium, (2) advance, and (3) retreat.
- Determine how multiple advance-retreat cycles affect the record of glacial moraines (end moraines).
  - Describe how end moraines form.
  - Discuss how more recent, large advances can impact moraines left by older, smaller advances.
  - Given an illustration of 3-4 end moraines, determine the most likely order of their formation and justify your ordering.